3. Creating Alarm types

When you have defined the alarm scenario, start by creating a new **alar m type** in the first step.

Alarm Types Overview

The administration of the alarm types is located in the **Workflows** area.

In the alarm type overview, you can create new alarm types and edit, deactivate/activate or delete existing ones.

Create Alarm Types

To create a new alarm type, click on the corresponding button at the top right.

First you have to determine whether it is an **alarm** or **information**.

Give the alert type a name, abbreviatio n (short key), sort key, priority, descri ption, and icon.

They should be unambiguous to avoid confusion.

The **sort key** determines at which position the alarm button will appear in the EVALARM App.

For all functions in EVALARM: The higher the sort key, the higher up the element.

You can choose between priority 1, 2 or 3. This has an influence on the sorting of the active and stopped alerts. This means, when there are several active or stopped alerts, the alarms of alarm types with a higher priority are displayed further up.

In addition you have the possibility to stop several active alerts of **priority 3** si multaneously with **multi-selection** in the mobile app as well as in the web cockpit.


Furthermore you can connect an alarm type to one or more building sectors. As a result you have the possiblity to select this structure when creating an alarm. The connecting can also be done in the **building sector**.

You also have the option of adding an attachment (pdf file) to the alarm type. This is always sent and can be opened up by the user in the alarm under the "Details" tab.

Finally go to "Create".








? Unbekannter Anhang

Once the alarm type is created, the next step is to customize the alarm ringtone.

The following ringtones are available besides the silent function:

Default, Speech, Fire, Fire in Morse, Info, Update



Then you have the possibility to enable the **Merge alarms** feature. By activating this function for an alarm type, several alarms of this alarm type in the same building sector are automatically grouped into one alarm.

This brings the advantage, if for example the fire alarm system triggers serveral detector groups in one building sector, EVALARM will i.e. only create one alarm with 10 marked dectector groups instead of 10. As a result the overview in an emergency situation is increased.

The function **Allow duplicates** allows that the same user can create several alarms from the same alarm type. This function makes sense for frequent or long active alarms like technical faults.

From the functions Merge alarms and Allow duplicates can only be one activated at the same time.

Enable GPS position of alarm creator

With this function you have the option of automatically sending the current GPS position of the alarm creator when the alarm is created.

It is a unique GPS position of the alarm creator at the time the alarm was created. There is no tracking of the alarm creator.

To use the function for the alarm type, activate the corresponding button.

Set up alarm levels

Alarms can be (de-)escalated via **alarm** levels.

Define appropriate alarm levels for alarm scenarios and create them here in the alarm type. Later, when configuring the workflows, you can then use them to trigger a workflow.

ADDITIONAL INFORMATION PARTICIPATION OPTIONS WORKFLOWS
Alarm
Fre
FIRE
100
1
Main Building
Behaviour in case of fire.pdf
8
Celost Uppede Default Seloct Sepecto
Update
٥
Ø

Icon Fington Nerge stars 0 O Fington Nerge stars 0 O Fination Kative Cative Cative



Set up additional information

Additional information are questions or relevant information that can be added by all those involved directly when the alarm is triggered or later when the alarm is active. Define all relevant questions and information that you consider necessary in the alarm scenario and create them here. You can store up to 5 optional answers for each additional information. These are text modules that allow users to add additional information more easily and quickly.

Later in the active alarm, all those involved have the same information about the supplemented additional information at their disposal.

Participation options

The participation options provide the users the possibility to give different respones, for example the arrival time at the site of incident.

In the alarm type can be added up to four different response options.

The options are text boxes and can be defined on own needs.

Examples are: 5 minutes, 10 minutes, already on-site, etc.

(1)

The participation options are only an optional function, that means if there are no participation options defined for an alarm type, the users still have the possibilty to simply accept or reject the alarm.

If participation options are set up for an alarm type, the users can select them by accepting an alarm as shown on the right site.

DETALS AARMLEVELS ADDITIONAL INFORMATION PARTICIPATION OPTIONS WORKFLOWS

Please feel free to add any more additional information				
Sort key	Question	Answers	Actions	
90	Is the Fire Department informed?	Yes, No	0	
80	Are there injured or dead persons?	No, Yes:	0	
70	Are nearby buildings in danger?	Yes, No	0	
50	Cause of fire?	Problems with electric wireing, cigarettes/ ash, the following chemicals:, welding	0	
10	Additional Information		0	

HOME WORKFLOWS	USERS LOCATION MANAGEMENT	LOGS	Administration Cockpit ?
ALADM TYPES OVERVIEW	X TECTALADM		

DETAILS ALARM LEVELS ADDITIONAL INFORMATION PARTICIPATION OPTIONS WORKFLOWS

Sort key	Name	Actions
100	5 minutes	0
90	10 minutes	0 💿
80	15 minutes	0 💿
70	Already on-site	0

0	
12:15 😰 ¥ कि.⊪ 94% ∎	
Alarm STOP	
Participation options	
Accept	
5 minutes	
10 minutes	
15 minutes	
Already on-site	
Attachments	
Details Receivers Tasks FD-Plan	
TESTALARM	
ACTIVE Loodenid of GA 07 2019 12:14	End the alarm
DETAILS USERS TASK LISTS MAPS ATTACHMENTS WORKFLOWS	
Accept Reject Smindles D	Reload
10 minutes 15 minutes Arready on-site Created by Extra 2019 2114	

Afterwards the respones are displayed directly under each user.

Furthermore it is possible to fold in and out the lists "Accepted", "Rejected" and "No response" and the number of users of every list is displayed on the right site.

