



# Access Permissions to EVALARM Clients




= authorized
  = can be configured

# User Role Permissions for Alarms



■ = authorized   
 ■ = not authorized   
 ■ = can be configured

# User Role Permissions for Additional Modules SOS\*, Evacuation\* & Dead Man's Switch\*



■ = authorized   
 ■ = not authorized   
 ■ = can be configured

\*this feature requires an additional license

# Summary



= authorized



= not authorized



= can be configured

\*this feature requires an additional license

	Super Administrator	Super User	Administrator	Crisis Team Supervisor	Crisis Team Member	Employee	Guest
Company overview	✓	✓	✗	✗	✗	✗	✗
Use of EVALARM App	✗	✗	✓	✓	✓	✓	✓
Web console - Cockpit	✓	✓	✓	✓	✓	✗	✗
Web console - Administration	✓	✗	✓	✳	✳	✗	✗
Create alarm/information	✓	✓	✓	✳	✳	✳	✳
Update alarm	✓	✓	✓	✓	✓	✗	✗
End alarm	✓	✓	✓	✓	✗	✗	✗
Receive push-notification (App)	✗	✗	✓	✓	✓	✓	✓
Receive E-Mail	✓	✓	✓	✓	✓	✓	✓
Show alarm archive (App)	✗	✗	✓	✓	✓	✓	✓
Show external alarms	✓	✓	✓	✓	✓	✗	✗
Update external alarms	✓	✓	✗	✗	✗	✗	✗
Show contact lists	✓	✓	✓	✓	✓	✓	✓
Show task lists	✓	✓	✓	✓	✓	✓	✓
Show FD-plan	✓	✓	✓	✳	✳	✳	✳
Show route maps	✓	✓	✓	✳	✳	✳	✳
Create SOS*	✓	✓	✓	✳	✳	✳	✳
Create evacuation*	✓	✓	✓	✳	✳	✳	✳
Show evacuation*	✓	✓	✓	✓	✓	✗	✗
Manage evacuation*	✓	✓	✓	✓	✓	✗	✗
Dead Man's Switch*	✓	✓	✓	✳	✳	✳	✳